

12/02/2021

C.S.E. Carel Central and Southern Europe



## humiSteam basic (UEY) with probe reading

---

### New software version for UEY

In order to respond adequately to the requests received from the market, it has been decided to implement the main probe reading on the humiSteam Basic (UEY) humidifier.

The range of electrode humidifiers is now even more competitive when a stand-alone isothermal humidifier with humidity reading from probe is required.

The improvements have already been released and are currently in production.

The manual has been updated and is available on the [carel.com](http://carel.com) website

#### Technical information:

The probe must be connected to terminals M2.1, M2.2 and M2.3 on the controller.

To enable the probe, set parameter A0.

To select the type of probe used (0-10 V, 2-10 V, 0-20 mA, 4-20 mA), set parameter A2.

Please do not hesitate to contact us for any further information.

Best regards

C.S.E. – Central & Southern Europe  
[sales.cse@carel.com](mailto:sales.cse@carel.com)